

Home / Programming / Built-in Examples / **Blink**

Privacy Policy

Blink

Terms Of Service

Turn an LED on and off every second.

Last revision • 02.09.2022

This example shows the simplest thing you can do with an Arduino to see physical output: it blinks the on-board LED.

Hardware Required

Arduino Board

optional

LED

220 ohm resistor

Circuit

This example uses the built-in LED that most Arduino boards have. This LED is connected to a digital pin and its number may vary from board type to board type. To make your life easier, we have a constant that is specified in every board descriptor file. This constant is LED_BUILTIN and allows you to control the built-in LED easily. Here is the correspondence between the

ON THIS PAGE

Security

Hardware Required

Cookie Settings

Circuit

Schematic

Code

Learn more

Hilfe

1 von 6

/



Q

D13 - 101

D13 - Due

D1 - Gemma

D13 - Intel Edison

D13 - Intel Galileo Gen2

D13 - Leonardo and

Micro

D13 - LilyPad

D13 - LilyPad USB

D13 - MEGA2560

D13 - Mini

D6 - MKR1000

D13 - Nano

D13 - Pro

D13 - Pro Mini

D13 - UNO

D13 - Yún

D13 - Zero

If you want to light an external LED with this sketch, you need to build this circuit, where you connect one end of the resistor to the digital pin correspondent to the *LED_BUILTIN* constant.

Connect the long leg of the LED (the positive leg, called the anode) to the other end of the resistor. Connect the short leg of the LED (the negative leg, called the cathode) to the GND. In the


1




Q

the LED_BUILTIN value.

The value of the resistor in series with the LED may be of a different value than 220 ohms; the LED will light up also with values up to 1K ohm.



Schematic



Code

After you build the circuit plug your Arduino board into your computer, start the Arduino Software (IDE) and enter the code below. You may also load it from the menu File/
Examples/01.Basics/Blink .
The first thing you do is to initialize LED_BUILTIN pin as an output pin with the line

```
pinMode(LED_BUILTIN,
OUTPUT);
```

In the main loop, you turn the LED on with the line:

```
digitalWrite(LED_BUILT
IN, HIGH);
```



Q /

LED anode. That creates a voltage difference across the pins of the LED, and lights it up. Then you turn it off with the line:

digitalWrite(LED_BUILT
IN, LOW);

That takes the LED_BUILTIN pin back to 0 volts, and turns the LED off. In between the on and the off, you want enough time for a person to see the change, so the delay() commands tell the board to do nothing for 1000 milliseconds, or one second. When you use the delay() command, nothing else happens for that amount of time. Once you've understood the basic examples, check out the BlinkWithoutDelay example to learn how to create a delay while doing other things.

Once you've understood this example, check out the **DigitalReadSerial** example to learn how read a switch connected to the board.





```
1
       /*
 2
         Blink
 3
 4
         Turns an
 5
       LED on for
 6
       one second,
 7
       then off for
 8
       one second,
 9
       repeatedly.
10
11
         Most
12
       Arduinos have
13
       an on-board
14
       LED you can
15
       control. On
16
       the UNO, MEGA
       and ZERO
17
18
         it is
19
       attached to
20
       digital pin
21
       13, on
       MKR1000 on
22
23
       pin 6.
24
       LED_BUILTIN
25
       is set to
26
         the correct
27
       LED pin
28
       independent
29
       of which
30
       board is used.
         If you want
31
32
       to know what
33
       pin the on-
34
       board LED is
35
       connected to
36
       on your
37
       Arduino
38
         model,
       check the
```

See Also

Learn more

You can find more basic tutorials in the **built-in examples** section.

You can also explore the language reference, a detailed collection of the Arduino programming language.

1





Q